

(SW-OPOS)Setup OPOS Driver(RS232)(VC)

Purpose

The document is aimed to illustrate the procedure for setup OPOS driver and test output.

Scope

This document is applicable to FS310, WD100, WD200, WD300, SD120, SD320, SD500, SD700, SG100, SG300, SG700, LG100, LG300, LG610, LG710, V-1010, V-1030, MIR3+ and IG620 with RS-232 or Virtual COM interface.

Requirements

- Scanner + RS-232/USB Cable
- PC + MS-Windows + RS-232/USB Port
- File: OPOS CCOs.msi
- Register File: ChampSCANNERSORegistry.exe
- Demo File: ChampSCANNEROPOSDemo.exe

Procedure


A. Check COM Port Number

-Connect the scanner on PC.


-Check the COM Port Number:

a. For RS-232, ensure the connected COM Port number.

b. For Virtual COM, open "Device Manager" and check the allocated COM Port number. In the case below, the COM Port number is allocated at 9.



The available COM Port number should be at COM1~COM9. If the allocated COM Port number is greater than 9, change it within 9. Right-click on "STMicroelectronics Virtual COM Port (COM)". Click: Properties -> Port Settings -> Advanced -> COM Port Number. Select a COM Port Number within 9.



-Remove the scanner power and connect again to initial settings.


B. Install Driver

-Double-click "OPOS_CCOs.msi" and follow the wizard to finish the installation.


-Right-click "ChampSCANNERSRegistry.exe" and execute with administrator privilege.

-On "Register Page", click "Register" to register scanner.


-When register successfully, click "OK".



- On "Interface Setting Page", select corresponding COM Port.
- For MIR3+ series products, such as IG620, set Baudrate at "115200" by default.
- Click "Save Setting" to save the settings.
- When save successfully, click "OK".



- On "Output Character Setting Page", select proper settings. Click "Save Setting" to save the settings.
- When save successfully, click "OK".



- Click "Exit" to exit the program.

